



SSD Utility Release Notes

Version: 2.3.2963 Release: October 25, 2017

Improvements

This is a maintenance release of SSD Utility, with the following enhancements:

Support added for TR200.

Fixed an instance where TL100 SSD graphic would disappear.

Updated company and copyright information.

Known Issues

Downgrade warning may be displayed when upgrading to a firmware version with alphabets (e.g. 12.a, 12.b). But it is actually an upgrade. (July 27, 2021)

TL100 Firmware update may fail on Windows 7 if the Intel® RSTe driver is installed. To work around this, use bootable SSD Utility to perform the update.

TL100 benchmark results may degrade if re-run immediately after a previous benchmark. Workaround is to wait a minute or two before re-running the benchmark.

On some PCs it is impossible to perform secure-erase: this happens if the PC BIOS issues SECURITY FREEZE LOCK the drive, and does not implement the suspend/resume cycle used to unfreeze it. Workaround is to use the secure erase feature in the BIOS if there is one, otherwise to perform secure erase on another PC.

On some laptops with dual Intel® & NVIDIA® graphics, SSD Utility may crash. This can be fixed by updating the Intel & NVIDIA drivers.

The mouse cursor is not displayed when using Bootable SSD Utility with a DisplayPort™ connection with a GeForce® 1070. Workaround is to boot in safe mode.

- Intel is a trademark of Intel Corporation or its subsidiaries.
- NVIDIA and GeForce are a registered trademark of NVIDIA Corporation.
- DisplayPort is a registered trademark of Video Electronics Standards Association (VESA®) in the United States and other countries.
- All other company names, product names and service names may be trademarks of their respective companies.